

Stamp With Gail

stampwithgaildigital.com

SCRAPBOOK

FINISHED SIZE: 8 X 5.25 X 2.75" with magnetic flap closure and 5 pages

Cover (Use medium weight chipboard)

- (2) 7-3/4 X 5-1/4 Front & Back
- (1) 5-1/4 X 2-3/4 Spine Back
- (1) 5-1/4 X 2-7/8 Spine Front
- (1) 5-1/4 X 2-1/4 Scallop Flap (Optional: Edges can be cornered)

Tyvek (Support)

- (4) 5-1/4 X 3"

Binding Hinge

- 11 X 5"
- Score from edge in sets as follows 2", 1/2", 1/2" 1/2" (gusset is 1/2")
- Continue moving across the page, score next 3 sets 1/2", 1/2", 1/2"
- Score last (6th) set 1/2" 1/2"
- Measure 2" from the last score line and trim off remaining card-stock.

Base Page

- (5) 7-1/2 X 5

Page Pocket

- (5) 7 X 6" (adhere to base Page for hinge attachment & create an end pocket)
- Score 1/2" on both long ends
- Finished size 7 X 5"

Belly Band

- 6 X 2"
- Score short ends 1/2"

Single Flap - End

- 7-1/2 X 5
- Score 1/2" on small end
- Finished size 7 X 5

Stamp With Gail

stampwithgaildigital.com

Single Flap - Top or Bottom

- 7-1/2 X 5
- Score 1/2" on long end
- Finished size 7 X 5

Scallop End Flap

- 5 X 2.5"
- Scallop edge with punch or leave as straight edge (print & cut scallop flap from PDF file at: <http://www.stampwithgaildigital.com/scrapbook-freebies>)
- Score 1/2" on long end

Scallop Top or Bottom Flap

- 7 X 2.5"
- Scallop edge with punch or leave as straight edge (print & cut scallop flap from PDF file at: <http://www.stampwithgaildigital.com/scrapbook-freebies>)
- Score 1/2" on long end

Scallop Book Flap

- 6-1/2 X 2.5"
- Scallop edge with punch or leave as straight edge (print & cut scallop flap from PDF file at: <http://www.stampwithgaildigital.com/scrapbook-freebies>)
- Score 1/2" on long end

Double Fold Flap (We did not make this in SWG Class)

- 7 X 5-1/2" & Score 1/2" on one short side
- 7-1/2 X 5" & Score 1/2" on one long side
- Finished size 7 X 5

Book Page

- 8-1/2 X 6-3/4 & Score at 4-1/4"
- Finished size 6-3/4 X 4-1/4

Book Belly Band

- 4.75" X 1.5", Score ends 1/2"

Stamp With Gail

stampwithgaildigital.com

SCRAPBOOK CUTS

Pocket (Cut 2) Inside Cover & Back of Page Pocket for Book

- 6 X 4.5
- Score 1/2" on each short side
- Score 1/2" on 1 long side
- Finished size 5 X 4"

Pocket Inside Back Cover

- 5 X 3"
- Score 1/2" on each short side
- Score 1/2" on 1 long side
- Finished size 4 X 2-1/2"

Making the Page Hinge Gusset

- Crease each score mark and burnish using a bone folder.
- Fold score marks, folding Valley, Mountain, Valley folds and repeating until you reach the end of your hinge.
- On your binding hinge, attach sticky tape to the first 1/2" score mark of each set. (5 score marks). Place tape next to the score mark, not on the score mark.
- Fold the first taped 1/2" section upward, adhering it to the next un-taped 1/2" section. This will be a valley fold. Repeat adhering each taped section to the next 1/2" un-taped section. This will make 5 hinges and 4 gussets.
- Burnish valley folds with bone folder
- Place score tape across the back of the hinge gusset and tape along the edges. Cover all or most of the entire back side. This side will be adhered to the cover spine.
- Trim the 4 edges of the hinges from the end of the hinge (be careful not to cut the hinge) to the edge of the first score mark, cutting on an angle (mitre the ends).
- Trim (mitre) each of the hinge edges cutting on an angle.
- Remove the backing from the score tape, center hinge over the Tyvek back spine cover and adhere.
- Burnish the 1/2" sections to insure tape is firmly attached to the binding.
- Add score tape to both ends of the hinge flaps. Tape slightly below the top edge.
- You are now ready to cover the scrapbook with plain paper and attach the pages.

Stamp With Gail

stampwithgaildigital.com

SCRAPBOOK CUTS

Making the Scrapbook Cover

- Lay out your chipboard cover pieces in correct order
- Place several strips of double sided tape on each side edge of the Tyvek. Place a strip of double sided tape on the side edge of each piece of chipboard that butts against the tyvek strip.
- Width between all chipboard cover pieces is the width of the side of a ruler
- Center the spine front onto on piece of cut Tyvek. Match top and bottom edges. Adhere.
- Butt ruler edge along side front spine, left edge. Place chipboard front cover against ruler and match top and bottom edges of tyvek. Adhere.
- Butt ruler against front spine, right edge. Place back cover, left side, against ruler. Line up top and bottom edges with tyvek. Adhere.
- Place ruler edge in center of 6" tyvek sheet. Place left scallop flap edge along the right side of the ruler and adhere flap. The tyvek should not be visible on the right side, top or bottom of the scallop flap.
- Run vertical lines of sticky tape along the left edge of the tyvek to 1/8" from the edge of the ruler.
- Butt the right edge of the front spine (it's attached to the other tyvek sheet) against the ruler and adhere front spine to the tyvek.

Covering the Scrapbook Cover

- Cut card stock paper in the same color as the base page. Usually black or craft paper.
- (1) 8.5 X 11", score paper: short end at 1.75", and top long side 1-5/8"
- (1) 8.5 X 11" score paper: top long side 1-5/8" and bottom long side 1.5", NO score on short end.
- (1) 8.5 X 5", score short end 1.5" & other short end 1-5/8", score long end at 1.25". Cut out corner square.
- Place score tape along the edges of the paper.
- With tape showing upward, center the cover binding onto the 8.5" paper .
- Place 1/2" score tape along the edges of each piece of chipboard. And vertical strips on each end of the chipboard sections that bend. Adhere chipboard to paper.
- Mitre each corner of the paper by cutting across the edge of the corner. Do Not cut entirely to the corner edge, leave a little bit of space or your chipboard corner will not be covered with paper.
- Fold down paper edges to the inside of the binding adhering to chipboard pieces.
- Adhere the Hinge with pages to the center of the back spine piece. Make sure the back of the hinge is covered with score tape.
- Add magnets to the flap and front cover for the closure. Adhere with glue and tape.
- Cut patterned paper 1/4" smaller than each of the chipboard pieces. Cut pieces for both the inside and outside and adhere with score tape.

Stamp With Gail

stampwithgaildigital.com

SCRAPBOOK CUTS

Adding the Pages to the Hinges

- Place your pages in the page order they'll be placed in the scrapbook. Make sure you have the cover sitting in front of you in the correct direction with the front cover to the left.
- Open the page from the bottom, remove the tape from both sides of one flaps/hinges and place the page onto the hinge. Set the page into the hinge so the page sits flat against the cover.
- Repeat placing all the pages on a hinge.

Finishing the Scrapbook

- Use patterned paper and embellishments to cover the pages.
- Make journaling cards to fit in the pockets and belly bands
- Make pull out pocket cards & frames for pictures
- Add miniature scrapbooks to pockets
- Embellish the front cover.